



Muse Developer Resources

 Search this site

Navigation

- Home
- SDK Overview
- Download & Install
- Getting Started
- LibMuse
- MuseIO
- MuseLab
- MusePlayer
- MuseIO Receiver
- Muse Hardware
- Muse Data Files
- Muse Communication Protocol
- Multi-Muse Setup
- Developer FAQ
- Intro to BCI and EEG
- Release Notes
- Forums
- Mailing List
- Support

[MuseIO](#) >

Available Data Modes (Presets)

Muse can be configured by MuseIO in different ways by specifying “--preset <PRESET>” as an option on the command line. The following presets are available:

SPS = samples per second

Remain

	Preset ID	EEG Channels	EEG Data	Accelerometer Data	Notch Filter
Consumer Presets	10	TP9, Fp1, Fp2, TP10	10 bits @ 220Hz	None	60Hz
	12	TP9, Fp1, Fp2, TP10	10 bits @ 220Hz	50Hz	60Hz
	14	TP9, Fp1, Fp2, TP10	10 bits @ 220Hz	50Hz	60Hz
Research Presets	AD	TP9, Fp1, Fp2, TP10	16 bits @ 500Hz	50Hz	OFF
	AE	TP9, Fp1, Fp2, TP10, DRL, REF	16 bits @ 500Hz	50Hz	OFF

Comments

You do not have permission to add comments.

[Sign in](#) | [Recent Site Activity](#) | [Report Abuse](#) | [Print Page](#) | Powered By [Google Sites](#)